Subject: Oversights in adding IOSTAT_END and IOSTAT_EOR
From: Van Snyder

1 Introduction

Two places were overlooked when the IOSTAT_END and IOSTAT_EOR parameters were added to 13.17.2.

2 Edits

Edits refer to 00-007. Page and line numbers are displayed in the margin. Absent other instructions, a page and line number or line number range implies all of the indicated text is to be replaced by immediately following text, while a page and line number followed by + indicates that immediately following text is to be inserted after the indicated line. Remarks for the editor are noted in the margin, or appear between [and] in the text.

Replace by 206:39-40

(3) If the input statement contains an IOSTAT= specifier, the variable specified is assigned the value of the named constant IOSTAT_END from the ISO_FORTRAN_ENV intrinsic module (13.17.2).

Insert "or end-of-file condition (9.5.3)" after the second "(9.5.3)." 207:2

Replace by 207:9-10]

(4) If the input statement contains an IOSTAT= specifier, the variable specified is assigned the value of the named constant IOSTAT_EOR from the ISO_FORTRAN_ENV intrinsic module (13.17.2).